

Week 4 — Calibration & Baselines (Step-by-Step Manual)

Week 4 — Calibration & Baselines (Step-by-Step Manual)

This week you'll turn your motion-tracking MVP into a **reliable** monitor by:

- establishing **perfish baselines** (what "normal" looks like),
- tuning **noise filters** (bubbles, reflections, plants),
- setting **day/night aware alerts** that reduce false alarms,
- documenting a **stable configuration** you can reuse.

> Prereqs: Week 2 metrics flowing into InfluxDB (`fish\_activity` with `distance\_px` per fish_id per minute) and a basic Grafana dashboard.

■ Objectives

1. Gather 3–7 days of data with consistent lighting and placement.
2. Quantify perfish **normal** activity (median/percentiles per time-of-day).
3. Tune the motion pipeline (thresholds, masks) to minimize noise.
4. Implement **dynamic alerting**: deviations vs. each fish's own baseline.
5. Freeze a **v1.0 config** (values + Grafana alert rules).

0) Prep: Snapshot your current config

Action: Save current parameters so you can compare before/after.

- In your project folder (`~/fish-monitor`), copy the code as a dated snapshot:

```
```bash
```

```
cd ~/fish-monitor
```

```
cp motion_track_influx.py motion_track_influx.v1.preweek4.py
```

```
git init 2>/dev/null || true
```

```
git add . && git commit -m "Pre-Week4 snapshot"
```

```
```
```

Context: Easy rollback point before tuning begins.

1) Lock the scene (camera + lighting hygiene)

Action: Make the scene predictable so algorithm tuning lasts.

- Fix **camera position** and angle; reautofocus once, then keep it.
- Use **one** lighting source (tank LED). Avoid ambient daylight swings.
- Turn off decorative air stones during calibration if they create bubbles in FOV.
- Wipe glass (inside/outside) and clean lens.

Context: Stable optics reduces mask/threshold tightness and false motion.

2) Add two quick filters in the code

Action: Reduce noise before retuning thresholds.

Open `motion\_track\_influx.py` and add:

- **ROI mask** (ignore static corners/surfaces that flicker):

```
```python
```

```

After capturing a frame once, build a binary mask of the tank region only.
Example (simple rectangle); refine to your tank shape if needed.
mask = np.zeros((FRAME_H, FRAME_W), dtype=np.uint8)
cv2.rectangle(mask, (40, 40), (FRAME_W-40, FRAME_H-40), 255, -1) # shrink edges
Later, apply mask to threshold image: th = cv2.bitwise_and(th, th, mask=mask)
...

- **Opening (erode->dilate) to kill speckles**:
```python
kernel = np.ones((3,3), np.uint8)
th = cv2.morphologyEx(th, cv2.MORPH_OPEN, kernel, iterations=1)
...

Also consider raising:
```python
MIN_CONTOUR_AREA = 300 # start 300-600 to ignore micro-bubbles
...

Context: You want fewer, larger blobs that map better to actual fish.

3) Choose working resolution & FPS
Action: Pick a sustainable processing rate.
- Start at **1280x720 @ 15-20 fps** in OpenCV:
```python
cap.set(cv2.CAP_PROP_FRAME_WIDTH, 1280)
cap.set(cv2.CAP_PROP_FRAME_HEIGHT, 720)
cap.set(cv2.CAP_PROP_FPS, 20)
...

- If CPU is spiky, drop to 960x540 or reduce FPS.
**Context:** Stable throughput keeps tracking IDs consistent.
---

## 4) Collect baseline data (3-7 days)
**Action:** Let the service run undisturbed.
- Ensure the systemd service is active:
```bash
sudo systemctl status fish-track
...

- Confirm points arrive in Influx:
 - Bucket `fish`, measurement `fish_activity` with tags `fish_id`, field `distance_px` (per minute).
Context: You'll use this data to compute per-fish baselines & time-of-day profiles.

5) Compute baselines (median & percentiles per fish, per hour)
Action: Derive robust baselines with Flux or Python. Below are two options.
Option A – Flux in Grafana (fast, no export)

```

Create a panel query (adjust range to last 7d):

```
```flux
import "experimental/aggregate"

fish = from(bucket: "fish")
  |> range(start: -7d)
  |> filter(fn: (r) => r._measurement == "fish_activity")
  |> filter(fn: (r) => r._field == "distance_px")

// Hour-of-day baseline per fish_id
fish
  |> map(fn: (r) => ({ r with hour: int(v: hour(t: r._time)) }))
  |> group(columns: ["fish_id", "hour"])
  |> quantile(q: 0.5, method: "exact_selector")          // median
```
```

Duplicate with `q: 0.1` and `q: 0.9` for P10/P90 bands. Overlay median and bands per fish.

### Option B – Python (export & crunch)

If you prefer CSV + Python (on your laptop or Pi):

- Export last 7d from Grafana Explore (as CSV).
- Use pandas to compute median/P10/P90 per fish\_id + hour.
- Save a JSON with thresholds for reuse.

**Context:** Medians & percentile bands give you robust “normal” per fish and time of day.

---

## 6) Tune thresholds using baseline bands

**Action:** Convert baselines into alert thresholds.

- For each fish\_id and hour-of-day:
  - **Low-activity threshold** = `max(P10, 0.3 \* median)` as a guardrail.
  - **Severe inactivity** if distance\_px  $\approx 0$  for **N** consecutive minutes (start with N=10).
- If tank has lights-off period, set **night mode**:
  - Lower expectations at night (e.g., allow values near 0 without alert).
  - Implement via Grafana “time range” or a query condition on hour-of-day.

**Context:** Dynamic thresholds cut false alarms and tailor to each fish’s rhythm.

---

## 7) Grafana panels & alerts (dynamic rules)

**Action:** Build a per fish panel showing:

- last 24–72h `distance\_px`
- overlay median & P10/P90 bands for that hour

**Alert rule template:** (adjust to your Grafana/Flux version)

- Condition: `distance\_px` 10min mean **< threshold(fish\_id, hour)** for **10 min**
- Or: a **rolling zscore** alert where  $z < -2.0$  for 10 min.

**Flux helper for 10min mean:**

```
```flux
```

```

from(bucket: "fish")
  |> range(start: -24h)
  |> filter(fn: (r) => r._measurement == "fish_activity" and r._field ==
"distance_px" and r.fish_id == "3")
  |> aggregateWindow(every: 1m, fn: mean)
  |> aggregateWindow(every: 10m, fn: mean)
```


Context: Start conservative; you can tighten after observing a few days.

8) Validate with controlled tests

Action: Sanity■check alerts before trusting them.

- Temporarily **cover the camera** for 2-3 minutes → confirm no spurious “low activity” unless extended.
- **Gently net one fish** to reduce its movement for ~10-15 min → ensure alert triggers once, not flapping.
- Re-enable bubbles/decor **one at a time** and verify no false spikes.

Context: You want alerts that are **neither silent nor noisy**.

9) Freeze v1.0 configuration

Action: Persist your tuned values so they survive restarts and upgrades.

- In `motion_track_influx.py`, promote your final values:
 - `MIN_CONTOUR_AREA`, `MAX_ASSOC_DIST`
 - any **ROI mask** coordinates
 - chosen **FRAME_W/FRAME_H/FPS**
- Save a **config JSON** (for future AI phase) with your per■fish medians and thresholds.
- Commit to git:


```

```bash
git add .
git commit -m "Week4: tuned thresholds, masks, and baseline notes"
```

```


Context: A known■good state you can ship, restore, or compare later.

10) Optional refinements (nice wins)

- **Day/Night profiles:** separate baselines for light hours vs dark hours.
- **Smoothing:** exponential moving average (EMA) on distance to reduce jitter.
- **Zone metric:** count minutes near **top** vs **bottom** (future health signals).
- **Alert cool■downs:** avoid rapid repeat notifications.

■ Week 4 Checklist

- [] Scene stabilized (camera & lighting)
- [] ROI mask and morphological filtering applied
- [] Sustainable resolution/FPS chosen
- [] 3-7 days of data captured

```

- [ ] Median/P10/P90 baselines computed per fish & hour
- [ ] Dynamic alert thresholds configured in Grafana
- [ ] Alerts validated with controlled tests
- [ ] v1.0 config committed

**\*\*Outcome:\*\*** A robust, self-calibrated MVP with trustworthy alerts – ready for the AI upgrade in Phase 2.